

A Guide to MorePerfect
by Mark Shepard¹
Version 1.3
Copyright 1990 Simple Productions

Simple Productions
Arcata, California, USA

"MorePerfect" is a trademark of Simple Productions.
"WordPerfect" is a registered trademark of WordPerfect Corporation.

¹ Mr. Shepard has kindly granted permission to use MorePerfect freely and without registration. See the included SHEPARD EMAILS.PDF file.

WHAT IS MOREPERFECT?

MorePerfect is a power-packed add-on for WordPerfect. It places on your letter keys a special set of movement and edit commands, offering you unsurpassed editing capability.

With a single keystroke, you can move the cursor or delete – by character, word, line, sentence, paragraph, or page – forward or backward – without removing your hands from the letter keys!

Other single-stroke commands move the cursor by a line, a screen, or the entire document. And you gain fast access to old and new features like Cut and Paste, Center Scroll, Go Back, Undelete, Rewrite, and Bookmark.

MorePerfect can double your editing speed, yet it's easy to learn and use.

MorePerfect is for use with WordPerfect 5.0 and 5.1 only. USING MOREPERFECT WITH OTHER VERSIONS MAY LEAD TO LOSS OF DATA.

ABOUT OUR PROGRAM

Here is a list of files you should have:

README	Quick intro (ASCII text)
MP.WPK	MorePerfect keyboard
MP.WPM	MorePerfect startup macro

... and the file you are viewing now, GUIDE.PDF.

INSTALLING MOREPERFECT

1. Copy the files MP.WPK and MP.WPM to your WordPerfect directory. For example, from the DOS prompt in your WordPerfect directory, you could copy both files from drive A with COPY A:MP.* followed by RETURN (ENTER). You could also use WordPerfect's own copy function within List Files (F5).

Note: If you have been placing macro and keyboard files in a different directory, copy our files there instead. If WordPerfect later tells you it cannot find them, check the Location of Files menu in Shft-F1 Setup, to see if a different directory is named.

2. From within WordPerfect, press Alt-F10 (Macro), type "MP" and press (ENTER). This selects the MorePerfect keyboard. You can instead select the keyboard manually, through the Shft-F1 Setup menu.

MorePerfect will now be active. Commands may execute slowly the first time they're used, because WordPerfect must load them into memory.

TURNING OFF MOREPERFECT

You can turn off MorePerfect anytime to restore your original keyboard. Just press the Off Key, Alt-minus (top row). Or you can "unselect" the MorePerfect keyboard manually, through the Shft-F1 Setup menu. Return to MorePerfect with Alt-F10, "MP".

Note: If you wish to remove MorePerfect permanently, you must turn it off by one of the above methods BEFORE erasing the MorePerfect files.

A quicker, temporary way to turn off MorePerfect is to press WordPerfect's Ctrl-6 (top row). You can then return to MorePerfect by pressing that same key TWICE.

MOREPERFECT AND YOUR KEYBOARD

MorePerfect is ideal for touch typists. It never makes you remove your hands from typing position – though you'll have to stretch a bit.

On old-style keyboards, with the Control Key next to the A key, always use your left little finger to press Ctrl or Alt. On the newer, "extended" keyboards, use "two-hand" fingering instead. For example, for Alt-W, press Alt with your righthand little finger, and W with the usual lefthand finger.

Some users find the fingering of our Ctrl-key commands more convenient on the old-style keyboard. If you have an extended keyboard, you may wish to switch your CapsLock Key with your left Control Key. This can be done by a number of macro programs and keyboard utilities, including PC Magazine's IBMFIX.COM.

THE MOREPERFECT COMMAND SET

MorePerfect affords startling editing speed and power through several simple principles:

1. All movement and edit commands are located on the "typewriter keys," for instant access.
2. Lefthand keys act backward in the document, while righthand keys act forward.
3. Ctrl-letter keys move the cursor, while Alt-letter keys delete.

Combining the last two principles generates a "command matrix." This arrangement packs more power onto the keyboard than you ever thought possible, while maintaining simplicity and ease of use.

Unlike other word processors placing primary commands on the letter keys, MorePerfect does NOT work by mnemonics – B for "bold," P for "page," and so on. Instead, MorePerfect works by finger position. As you try the keys listed in the coming pages, you'll quickly catch on to the pattern, and you'll be able to locate commands without memorizing letter names. (If you ever need a quick reminder, just press F3 to access the MorePerfect keyboard chart.)

In the listings on the following pages, the WordPerfect equivalent key – if any – is noted in parentheses.

Note: MorePerfect displaces WordPerfect secondary commands on the Ctrl-letter keys, and user macros on most Alt-letter keys. WordPerfect's Compose Key, Ctrl-V, is moved to Ctrl-Backslash.

Still free are all the Alt-letter keys on the bottom row, plus Alt-A and Alt-Q. You can access the earlier key functions at any time by turning off MorePerfect, as explained earlier in this guide.

Also note: A few MorePerfect commands use WordPerfect's search function, cancelling search text you've entered earlier.

Some add then delete text – so F1 Cancel may not bring up all three of your most recent deletions. These inconveniences have been minimized. In most cases, you'll notice only how much easier WordPerfect has become.

THE UNIT KEYS

The most important set of keys in MorePerfect is the Unit Keys. These enable you to move the cursor or delete – by character, word, line, sentence, paragraph, or page – forward or backward – with a single keystroke.

Unit Keys always act to the START of a unit. For instance, if your cursor is in the middle of a sentence, Sentence Up will move it to the start of the same sentence. Repeating the command will move it to the

start of the previous sentence. Delete Sentence Down will delete from the cursor to the start of the next sentence.

When you move backward to the start of a unit, the cursor moves in front of any invisible codes placed there. When you delete backward, the codes too are deleted. (To first check for codes, press Alt-F3.)

CHARACTER KEYS

Ctrl-F Character Left (LeftArrow)
Ctrl-J Character Right (RightArrow)
Alt-F Delete Character Left (Backspace)
Alt-J Delete Character Right (Delete)

WORD KEYS

Ctrl-D Word Left (Ctrl-LeftArrow)
Ctrl-K Word Right (Ctrl-RightArrow)
Alt-D Delete Word Left (Home Backspace)
Alt-K Delete Word Right (Home Delete)

LINE KEYS

Ctrl-S Line Left (Home Home Home LeftArrow)
Ctrl-L Line Right (End)
Alt-S Delete Line Left
Alt-L Delete Line Right (Ctrl-End)

SENTENCE KEYS

Ctrl-R Sentence Up
Ctrl-U Sentence Down
Alt-R Delete Sentence Up
Alt-U Delete Sentence Down

Note: Sentence Up and Down normally recognize sentences ending in either a period, a question mark, or an exclamation point – but, if blocking is on, only a period works.

PARAGRAPH KEYS

Ctrl-E Paragraph Up
Ctrl-I Paragraph Down
Alt-E Delete Paragraph Up
Alt-I Delete Paragraph Down

PAGE KEYS

Ctrl-W Page Up
Ctrl-O Page Down
Alt-W Delete Page Up
Alt-O Delete Page Down

Note: The Delete Page commands ask you to confirm.

THE TRAVEL KEYS

The Travel Keys move you vertically through your document. All are Ctrl-letter keys. Travel Keys moving backward do NOT move in front of invisible codes.

CENTER SCROLL KEYS

Ctrl-T Center Scroll
Ctrl-Y Center Scroll

Now you can shift your display without moving the cursor to the screen top or bottom! The two Center Scroll Keys move the text with the cursor on it to center screen. The cursor stays in its place in the document, so your work isn't interrupted.

WordPerfect precludes the Scroll Up and Down commands we'd like to place on these keys, but you'll find Center Scroll a handy and flexible alternative. For instance, if used after a Screen Key (below), it will shift the display by just half a screen.

CURSOR KEYS

Ctrl-G Up (UpArrow)
Ctrl-H Down (DownArrow)

DOCUMENT KEYS

Ctrl-B Document Up (Home Home UpArrow)
Ctrl-N Document Down (Home Home DownArrow)

SCREEN KEYS

Ctrl-V Screen Up (Num Pad -)
Ctrl-M Screen Down (Num Pad +)

THE ACTION KEYS

The Action Keys perform a variety of functions to make typing and editing quicker and more convenient.

CUT AND PASTE KEYS

Ctrl-P Block On/Off (Alt-F4)

Alt-P Cut

Ctrl-[Paste

Use the Cut and Paste Keys with other MorePerfect keys for super-quick block operations. Turn on blocking with Ctrl-P, then extend the block with Unit or Travel keys. To shut off blocking, press Ctrl-P again. Or "cut" the block from the document with Alt-P. Press Ctrl-[to "paste" it back into the document, wherever you like and as often as you like – until you cut another block.

REWRITE KEY

Ctrl-] Rewrite

No more missing with your cursor! Like WordPerfect's Ctrl-F3 – but with a single stroke – this key rewrites the entire screen. Use it after adding or deleting text, to quickly bring your text back in line with the right margin and to reposition page breaks. (Many MorePerfect commands do this for you automatically.)

BOOKMARK KEY

Ctrl-C Bookmark

Bookmarks for WordPerfect! This key lets you insert, remove, and travel to any number of invisible bookmarks, anywhere in your document.

At the Bookmark menu, you can insert a bookmark into the document ("Place Bookmark") or travel backward or forward to a bookmark you have already inserted ("Bookmark Up" and "Bookmark Down"). After traveling to a bookmark, you can also delete it ("Remove Bookmark"), move to another bookmark, or return to the place in the document you just left ("Go Back").

Note: The bookmarks won't affect printing, so you can leave them in your document, if you prefer.

GO BACK KEY

Ctrl-X Go Back (Ctrl-Home Ctrl-Home)

A quick key for returning your cursor to its previous position. Handy if you accidentally jump elsewhere in the document.

UNDELETE KEY

Ctrl-Z Undelete

Like WordPerfect's F1 Cancel – but with a single stroke – this key restores your most recent deletion.

THE SUPPORT KEYS

The Support Keys help you use MorePerfect.

COMPOSE KEY

Ctrl-Backslash Compose (Ctrl-V)

This substitutes for WordPerfect's own Compose Key, Ctrl-V, which is displaced by MorePerfect.

OFF KEY

Alt-minus (top row) MorePerfect Off

This turns off MorePerfect and restores the original WordPerfect keyboard, along with any Alt-letter macros that MorePerfect displaced. Use it to access earlier key functions, then return to MorePerfect by pressing Alt-F10 (Macro) and typing "MP". For alternate methods, see the section in this guide, "Turning Off MorePerfect."

HELP KEY

F3 Help

MorePerfect adds its own help feature to WordPerfect. F3 now calls up a menu letting you choose between WordPerfect Help and MorePerfect Help. If you choose MorePerfect Help, a keyboard chart pops up for a quick reminder of MorePerfect commands. (To go directly to WordPerfect Help, you can ignore the menu and just press F3 twice.)