

Your Utilities & VGA Drivers diskette contains Windows drivers for the following video modes:

Driver Name	Resolution
16_1024.DRV (Multi-Resolution)	640x480, 16 Colors 800x600, 16 Colors (1) 1024x768, 16 Colors (1,2)
256_1024.DRV (Multi-Resolution)	640x480, 256 Colors (2) 800x600, 256 Colors (1,2)

- (1) Requires a multiple-frequency monitor
- (2) Requires 512KB of video memory

Installing the Windows 3.0 video drivers:

To install the drivers onto the hard drive, Windows 3.0 must first be installed. Then, perform the following steps:

1. Insert the video drivers diskette into drive A.
2. Type the following commands:  
A: [ENTER]  
CD \WIN30 [ENTER]  
VIDSETUP C:\windows [ENTER]

Note: "windows" specifies the directory containing Windows 3.0 and [ENTER] specifies the [ENTER] key.

3. The drivers are copied to your hard drive and a menu lists the available modes. Select the video mode you wish to use. Be sure your monitor can operate in the selected video mode.

Changing the Windows 3.0 video driver:

To use a different super VGA video driver, perform the following steps:

1. Type the following commands:  
C: [ENTER]  
CD \windows [ENTER]  
VIDSETUP [ENTER]

Note: "windows" specifies the directory containing Windows 3.0 and [ENTER] specifies the [ENTER] key.

2. A menu lists the available video modes. Select the video mode you wish to use. Be sure your monitor can operate in the

selected video mode.

(jej-05/11/94)□